

TimeClock Plus


Workstation Hub Installation

To operate items such as the **BioScan 7 Desktop Reader**, you will need to install a **Workstation Hub**. This hub connects remotely to your TimeClock Plus install, and will be the go-between that connects your fingerprint scanner to the system.

NOTE: This installation process will reboot the computer. Save all your work before proceeding.

Installing a Standalone Workstation Hub

- 1. On the computer that will operate the Digital Output scanner, run **tcp.installer.workstation-7.0.x.x.exe**. Depending on the version of the installer you are using, the numbers in the file name may vary.
- 2. Click **Next** on the welcome screen.
- 3. **Select Installation Folder**: Here, you will be prompted to choose a location to install Workstation Hub, or keep the default location. Click **Next**.



4. Configure API Server: This is where you will configure where the hub will connect.

Workstation Hub Installation Guide


© **Data Management, Inc. All Rights Reserved.** This document is confidential and shall not be duplicated, published or disclosed, in whole or in part, without prior written permission of Data Management, Inc. This documentation is subject to change without notice.



TimeClock Plus

- Host Address: This is the path to the TimeClock Plus API server. Normally, this path will look like https://[server]/api/v0000.
- Namespace: If you are using TimeClock Plus OnDemand, or if you are utilizing a system with multiple separate databases, then you may need to specify the namespace that the hub will connect to. If not, then this field can be left blank.

Click Next.




Workstation Hub Installation Guide

© **Data Management, Inc. All Rights Reserved.** This document is confidential and shall not be duplicated, published or disclosed, in whole or in part, without prior written permission of Data Management, Inc. This documentation is subject to change without notice.



TimeClock Plus

- 5. **Ready to Install**: This is the final screen before installation.
 - If you wish to change any settings, click Back, or if you wish to discontinue the installation, click Cancel.
 - If you need to check or change the ports that Workstation Hub and WebClock will use, click the **Configure Ports** button.




- 6. Click **Install**. The installer will then download the necessary components for TimeClock Plus Workstation Hub, as well as a local instance of WebClock, and drivers for the BioScan 7 reader.
- 7. After the installation is complete, you may be prompted to restart the computer.

Workstation Hub Installation Guide



TimeClock Plus

Browsing to Workstation Hub



- 1. On the desktop, locate and open the **TimeClock Plus Control Panel**.
- 2. In the Applications menu, choose Go to Workstation Hub.
- 3. Workstation Hub will then open in your default browser. You can then log in normally by using a user ID and password.
- 4. Alternatively, Workstation Hub can be accessed by browsing to http://[computer name]/app/workstation.

For assistance please call Customer Support at: (325) 223-9300 M-F, 7AM to 6PM Central Time, Excluding Holidays

Workstation Hub Installation Guide

© **Data Management, Inc. All Rights Reserved.** This document is confidential and shall not be duplicated, published or disclosed, in whole or in part, without prior written permission of Data Management, Inc. This documentation is subject to change without notice.